

# 光学设计软件**SYNOPSYS™**

安装说明



### 武汉墨光科技有限公司



Light Further

# 系统要求

- 操作系统: Window7/8/10。
- 内存: 4G(至少), 8G (典型)。如果进行对象非常复杂、物理光学或散射和照明分析时,最低要求是8G,最好是16G。
- 硬盘空间: 500G(至少)。
- 显卡: 分辨率1024 x 768 pixels(至少)。
- 其他:

- USB接口。

SYNOPSYS对于系统的要求不高,目前的主流配置 可以非常轻松顺畅的运行SYNOPSYS



### 安装文件

准备SYNOPSYS™的两个安装文件:

SYNOPSYS200\_v15.msi 和 InstallSYNOPSYSdll.msi

SYNOPSYS200\_v15.msi

注意:

1.初次安装,两个文件都要安装,并且SYNOPSYS200\_v15.msi要先安装。

(如果安装顺序弄反了,最后再多装一次InstallSYNOPSYSdll文件即可)

2.安装路径和文件夹名都不能出现中文

3.安装完成能使用后,后续想升级软件,只需要安装新版的SYNOPSYS200\_v15.msi 文件即可。



# 安装SYNOPSYS200\_v15

### 双击SYNOPSYS200\_v15.msi 安装包,弹窗如下,点击Next按钮



#### 2019/4/19 Copyright © Wuhan Asdoptics Science And Technology Co.,Ltd

slide 4





用户许可协议

#### 阅读用户许可协议

B SYNOPSYS™ Setup	$\times$
End-User License Agreement	
Please read the following license agreement carefully	0
LICENSE AGREEMENT FOR SYNOPSYS(tm) PROGRAM PACKAGE	
OPTICAL SYSTEMS DESIGN, INC., a Maine, USA, corporation, (VENDOR) hereby grants Customer a non-exclusive, non-transferable licence to use the SYNOPSYS(tm) computer program package (the Program) at specific computer installations, and to make and use copies of the program code in accordance with the terms and subject to the conditions attached hereto, for a fee set forth below. and Customer bereby accepts the License.	
• I accept the terms in the License Agreement	
◯ I do not accept the terms in the License Agreement	
Advanced Installer	
< Back Next > Cancel	



### 安装路径

### 选择安装路径(注意文件夹名和路径不要出现中文名字)

ider SYNOPSYS™ Setup	_		$\times$
Select Installation Folder			
This is the folder where SYNOPSYS <sup><math>TM</math></sup> will be installed.			0
To install in this folder, click "Next". To install to a different folder, enter i "Browse".	t below	or click	
<u>F</u> older:			
C:\SYNOPSYS\		Browse	
Advanced Installer			
< Back Next >		Cance	el



安装向导设置完成

# 准备安装,安装向导已经准备好开始SYNOPSYS的安装,点击"Install"开始安装。(部分操作系统,会有安装软件的弹窗警告,点击确定即可)

tien SYNOPSYS™ Setup	$\times$
Ready to Install	
The Setup Wizard is ready to begin the SYNOPSYS $^{\mathrm{M}}$ installation	
Click "Install" to begin the installation. If you want to review or change any of your installation settings, click "Back". Click "Cancel" to exit the wizard.	
Advanced Installer	
< Back	Cancel



# SYNOPSYS200\_v15安装完成

### 完成SYNOPSYSTM安装向导,点击"Finish"按钮退出安装向导。





# 安装InstallSYNOPSYSdll.msi

### 双击InstallSYNOPSYSdll.msi安装包,程序将自动运行安装 (部分操作系统,会有安装软件的弹窗警告,点击确定即可)

Install_SYNOPSYS_dll	
Please wait while Windows configures Install_SYNOPSYS_	dll
Gathering required information	
	Cancel



# 试用版

安装完成以后,在桌面找到SYNOPSYS软件的快捷方式,双击打

### 开软件。



Light Further



### 正式版

安装完成以后,请不要插上SYNOPSYS的硬件KEY。然后运行KEY的驱动程序。

单机版key驱动程序: Sentinel\_System\_Driver\_Installer\_7.60.exe

网络版key驱动程序(只在密钥服务器上安装)

Sentinel\_Protection\_Installer\_7.6.9

用户只需按照自己的KEY的版本,安装对应KEY驱动程序即可。



### KEY驱动程序安装

用户只需按照自己的KEY的版本,安装对应KEY驱动程序即可。(以下以单机版的KEY驱动程序安装为例,网络版的KEY驱动程序安装步

骤类似),双击KEY驱动程序,运行如下:



2019/4/19



KEY驱动程序安装向导

KEY驱动程序安装向导界面如下,点解Next





# KEY驱动程序选项

### KEY驱动程序安装选项,选择Modify,然后点击Next

🛃 Sentinel Syste	m Driver Installer 7.6.0	) - InstallShield \	Wizard	×
<b>Program Mainte</b> Modify, repair, o	enance or remove the program.		Ser	ntinel.
Modify	Change which program f Custom Selection dialog installed.	eatures are installe in which you can ch	d. This option display hange the way feature	s the es are
🔿 Repair	Repair installation errors corrupt files, shortcuts, a	in the program. Th nd registry entries.	nis option fixes missin	g or
O Remove	Remove Sentinel System	Driver Installer 7.6	5.0 from your comput	er.
InstallShield ———		< Back	Next >	Cancel



# KEY驱动程序特性选择

#### 自定义设置选择要安装的程序特性。

$\blacksquare$ Sentinel System Driver Installer 7.6.0 - InstallShield Wizard $ imes$				
Custom Setup Select the program features you want installed.	Sentinel.			
Click on an icon in the list below to change how a feature is insta	alled.			
Sentinel System Drivers USB System Driver	Feature Description The device driver for Sentinel keys.			
	This feature requires OKB on your hard drive. It has 0 of 2 subfeatures selected. The subfeatures require OKB on your hard drive.			
C:\Program Files (x86)\Common Files\SafeNet Sentinel\Sentinel System Driver\				
InstallShield				
Help < Back	Next > Cancel			



# KEY驱动程序准备安装

#### KEY驱动程序准备安装,点击 Install

륡 Sentinel System Driver Installer 7.6.0	) - InstallShield \	Wizard	×
Ready to Modify the Program			
The wizard is ready to begin installation.		Ser	nunel.
Click Install to begin the installation.			
If you want to review or change any of yo the wizard.	ur installation settir	ngs, click Back. Click (	Cancel to exit
InstallShield			
	< Back	Install	Cancel



KEY驱动程序安装完成

### KEY驱动程序安装安装完成后,界面如下,点击Finsh,即可退出。





正式开启程序

安装程序和驱动程序都安装完成以后,请重启电脑,然后在桌面找到SYNOPSYS软件的快捷方式 疑,双击打开软件即可正常使用。

可以关注我们的微信公众号,了解更多的资讯。







• 软件更新信息

Light Further